

```

*&-----*
*& Report   SAPBC425_TEMPLATE                               *
*&                                                *
*&-----*
*&                                                *
*&                                                *
*&-----*

REPORT   sapbc425_template                               .

DATA:
    wa_spfli TYPE spfli,
    it_spfli TYPE TABLE OF spfli WITH KEY carrid connid.

SELECTION-SCREEN BEGIN OF BLOCK carrier WITH FRAME TITLE text-car.
SELECT-OPTIONS: so_carr FOR wa_spfli-carrid.
SELECTION-SCREEN END   OF BLOCK carrier.

DATA: r_var TYPE REF TO zif_ex_bc42501.

*&-----*
*&   Event START-OF-SELECTION                               *
*&-----*
START-OF-SELECTION.
CALL METHOD cl_exithandler=>get_instance
    CHANGING
        instance = r_var.
IF sy-subrc <> 0.
    MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
        WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
ENDIF.

SELECT *
    FROM spfli
    INTO CORRESPONDING FIELDS OF TABLE it_spfli
    WHERE carrid IN so_carr.

*&-----*
*&   Event END-OF-SELECTION                                 *
*&-----*
END-OF-SELECTION.

LOOP AT it_spfli INTO wa_spfli.

    WRITE: / wa_spfli-carrid,
            wa_spfli-connid,
            wa_spfli-countryfr,
            wa_spfli-cityfrom,
            wa_spfli-countryto,
            wa_spfli-cityto,
            wa_spfli-deptime,
            wa_spfli-arrrtime.

    HIDE:   wa_spfli-carrid,
            wa_spfli-connid.

ENDLOOP.

```

```

AT LINE-SELECTION.
CASE sy-lsind.
  WHEN 1.
    CALL METHOD r_var->vl
      EXPORTING
        i_carrid = wa_spfli-carrid
        i_connid = wa_spfli-connid.
  ENDCASE.

```

```

*&-----*
*&                LZFGR00TOP                *
*&-----*

```

```

FUNCTION-POOL ZFGR00.                "MESSAGE-ID ..

```

```

*&-----*
*&                LZFGR00UXX                *
*&-----*

```

```

*****
*   THIS FILE IS GENERATED BY THE FUNCTION LIBRARY.           *
*   NEVER CHANGE IT MANUALLY, PLEASE!                          *
*****

```

```

INCLUDE LZFGR00U01.
      "Z_00SAMPLE_INTERFACE_00001421

```

```

*&-----*
*&                LZFGR_BTE00TOP            *
*&-----*

```

```

FUNCTION-POOL ZFGR_BTE00.            "MESSAGE-ID ..

```

```

*&-----*
*&                LZFGR_BTE00UXX           *
*&-----*

```

```

*****
*   THIS FILE IS GENERATED BY THE FUNCTION LIBRARY.           *
*   NEVER CHANGE IT MANUALLY, PLEASE!                          *
*****

```

```

INCLUDE LZFGR_BTE00U01.
      "Z_01SAMPLE_INTERFACE_00001350

```

```

*&-----*
*& Include          ZXBC425G00TOP          *
*&-----*

```

```

*&-----*
*& Include          ZXBC425G00U02         *
*&-----*

```

```

*&-----*
*& Include          ZXBC425G01TOP         *
*&-----*

```

```

tables sflight01.
data: seatsfree type sflight01-seatsmax.

```

```
*&-----*
*& Include          ZXBC425G01U01          *
*&-----*
IF flight-fldate < sy-datum.
call screen 9000.
  MESSAGE w011(bc425) WITH sy-datum.
ENDIF.

*&-----*
*& Include          ZXBC425G01U02          *
*&-----*
SUBMIT sapbc425_booking_01
WITH so_car = flight-carrid
WITH so_con = flight-connid
WITH so_fld = flight-fldate
AND RETURN.

*&-----*
*& Include          ZXBC425G01U03          *
*&-----*
sflight01 = flight.
seatsfree = sflight01-seatsmax - sflight01-seatsocc.
```